

DUMPS ARENA

Specialist - Systems Administrator PowerProtect DD Exam

EMC DES-DD33

Version Demo

Total Demo Questions: 7

Total Premium Questions: 54

Buy Premium PDF

<https://dumpsarena.co>

sales@dumpsarena.co

sales@dumpsarena.co
dumpsarena.co

QUESTION NO: 1

An administrator has retained snapshots for a single MTree and is trying to create a new one. An error message is received.

What is the reason for the failure?

- A. The maximum number of snapshots has been exceeded
- B. The DDOS needs to be upgraded
- C. The user does not have the permission to retain more snapshots
- D. There are not enough snapshot licenses

ANSWER: A**Explanation:**

The maximum number of snapshots allowed per MTree is 750. Warnings are sent when the number of snapshots per MTree reaches 90% of the maximum allowed number (from 675 to 749 snapshots), and an alert is generated when the maximum number is reached. To clear the warning, expire snapshots and then run the file system cleaning operation. Note: To identify an MTree that is nearing the maximum number of snapshots, check the Snapshots panel of the MTree page regarding viewing MTree snapshot information.

Reference: <https://www.delltechnologies.com/asset/en-us/products/data-protection/technical-support/docu95865.pdf>

QUESTION NO: 2

Where is the DD System Manager can the status of chassis components be found?

- A. Maintenance > Chassis
- B. Hardware > Chassis
- C. Health > Chassis
- D. Home > Chassis

ANSWER: B**Explanation:**

Reference: https://www.juniper.net/documentation/en_US/release-independent/junos/topics/task/verification/router-chassis-status-nog.html

QUESTION NO: 3

What are some possible network bottlenecks for a PowerProtect DD?

- A. Configuration, wire speeds, switches and routers
- B. Connectivity, firewalls, and routing protocols
- C. Connectivity, routing protocols, and configuration
- D. Routing protocols, switches and routers, and wire speeds

ANSWER: A

QUESTION NO: 4

An administrator wants to integrate a PowerProtect DD appliance into their current backup environment using CIFS, NFS, DD Boost, and VTL.

Which backup applications support these protocols?

- A. Commvault Simpana and Veritas Backup Exec
- B. Veritas NetBackup and Dell EMC NetWorker
- C. Dell EMC Avamar and Dell EMC NetWorker
- D. IBM Spectrum Protect and Veritas NetBackup

ANSWER: B

QUESTION NO: 5

A backup administrator needs to implement BoostFS for Windows.

What do they need to install on the Windows server? (Choose all that apply.)

- A. CBFS
- B. CIFS
- C. NFS
- D. FUSE

ANSWER: B C

Explanation:

For CIFS/NFS/DD BoostFS, the first consideration to address is what level of CIFS, NFS and DD BoostFS sharing is wanted for the DD series appliances.

Reference: <https://www.delltechnologies.com/asset/en-us/products/data-protection/technical-support/s-2416-dell-emc-powerprotect-dd-series-appliances-with-commvault-configuration-guide.pdf>

QUESTION NO: 6 - (DRAG DROP)

DRAG DROP

What is the correct sequence of steps to configure storage for Dell EMC Cloud Tier in the DD System Manager?

Select and Place:

Click "Configure" in the Cloud Tier section	STEP 1
Click "Add to Tier"	STEP 2
Select "Storage" under the Hardware tab	STEP 3
Under "Addable Storage", select the checkbox for the shelf to add	STEP 4

ANSWER:

	Click "Configure" in the Cloud Tier section
	Click "Add to Tier"
	Select "Storage" under the Hardware tab
	Under "Addable Storage", select the checkbox for the shelf to add

Explanation:

Reference: <https://www.delltechnologies.com/asset/en-us/products/data-protection/technical-support/docu95865.pdf>

QUESTION NO: 7

How can remote logging with a syslog server be configured on a PowerProtect DD system?

- A. Use the CLI command log host enable
- B. Use the DDSM to enable the remote logging
- C. Remote logging is enabled by default

D. Use the DDMC to enable the remote logging

ANSWER: A

Explanation:

Reference: <https://support.rocketcyber.com/hc/en-us/articles/360017916917-How-do-I-configure-syslog-remote-logging-for-a-Untangle-Firewall>